Documentation On how to control the Arduino Program

- 1. To move the robot:
 - Pass the command: m <Steps in int> <Speed in int> (<> not included)
 - Steps can be from 0 to infinite (800 is one revolution of tyre)
 - Speed can only be from 200 to 4000 (400 is recommended)
- 2. To rotate the robot:
 - Pass the command: r <Steps in int> <Speed in int> (<> not included)
 - Steps can be from 0 to infinite
 - Speed can only be from 200 to 4000 (400 is recommended)
- 3. To change the acceleration and de acceleration (default is 4000)
 - Pass the command: a <acceleration in int> (<> not included)
 - 1000 to 5000 is the limit
- 4. To immediately stop the motors regardless of the state:
 - Pass the command: n
- 5. To immediately reset the motors state and position regardless of the state:
 - Pass the command: s
- 6. To get the info on the stepper positions:
 - Pass the command: p
- 7. To Block the motors in place (Warning: Do not do it for a long time, the motors can get really hot and may be damaged)
 - Pass the command: b
- 8. To disable the block from the motors: (DO it as soon as you finish your movement, though I made it so that if you forget, the motors have a 30seconds auto turnoff)
 - Pass the command: d
- 9. TO change the mode from the steps to mm to move the motor and vice versa:
 - Pass the command: c